NORD SOFTWARE LIBRARY DISKETTE

. .

and the second second

CONTAINING : BACKUP-SYSTEM

رائسها العاجي الم

DIRECTORY NAME : ND-10337B USER NAME : FLOPPY-USER

FILE 0 : (ND-10337B:FLOFFY-USER)BACKUF-SYSTEM-B:BFUN;1

16 NOVEMBER 1981

NORSK 1	DATA	A/S
---------	------	-----

## NORD SOFTWARE LIBRARY REVISION LOG

I

ļ

1

1		
PRODUCT	I NAME BACKUP-SYSTEM	! ND-NUMBER ! ! 10337B
	l BRCKOF-SISIEM	
! ISSUED	! DATE 81.11.16	BY (INITIALS) LA
!		
! REASON	! X ERROR CORRECTION	! . DIFFERENT ENVIRONMENT !
1	! X CHANGE/ADDITION	!
!	!	!!
! FILES	! PROG.NUMB. NAME	1
! CHANGED	! 203160B BACKUP-SYSTE	EM !
! OR NEW	1	1
! FILES	!	!
1	!	

## CHANGES

- LABELS ARE CHANGED TO INCLUDE MAX BYTE POINTER ALSO WHEN COPYING IN STANDARD VOLUME MODE. THIS WILL ENSURE CORRECT BYTE POINTER ON DESTINATION FILES WHEN INTERCHANGING TAPES BETWEEN BACKUP-SYSTEM AND SINTRAN COPY-USERS-FILES.
  - CORRECTED ERROR IN INPUT ROUTINE WHEN SELECTING FILES TO BE COPIED. FILE-TYPE WAS SOMETIMES IGNORED.
  - CORRECTED ERROR WHEN CHECKING ON OWNER OF VOLUME. USERS WITH NAMES LONGER THAN 13 CHARACTERS WERE NOT ALLOWED TO ACCESS THEIR VOLUMES.
  - ERRORS LIKE NOT-READ-ACCESS WHEN ACCESSING SOURCE-FILES CAUSED THE BACKUP-SYSTEM TO ABORT COPYING. THE BACKUP-SYSTEM WILL NOW PRINT THE FILE-NUMBER, ERROR MESSAGE AND CONTINUE COPYING THE FOLLOWING FILES.
  - WHEN SOURCE-FILES ARE DEFINED FROM A PARAMETER-FILE, THE BACKUP-SYSTEM WILL NOT TERMINATE IF NO FILES ARE FOUND UNDER A GIVEN FILE KEY. THE BACKUP-SYSTEM TERMINATES AT END OF PARAMETER-FILE.
  - MAG-TAPE UNIT WAS NOT RESERVED WHEN A COPY WAS EXECUTED FOLLOWING A LIST- OR CREATE-VOLUME COMMAND. THE MAG-TAPE UNIT IS NOW RESERVED WHEN ACCESSED AND STAYS RESERVED UNTIL A NEW UNIT IS ACCESSED OR EXIT FROM THE BACKUP-SYSTEM IS PERFORMED.
  - CHANGES HAVE BEEN MADE IN THE TAPE INPUT ROUTINES OF THE BACKUP-SYSTEM TO ACCEPT VARIOUS IMPLEMENTATIONS OF THE ANSI-LABEL STANDARD. THE BACKUP-SYSTEM WILL TURN ON MANUAL-CHECK IF FILES AND NAMES ARE INCOMPATIBLE WITH ND-FILESYSTEM. A POSSIBILITY TO REDEFINE THE NAMES IS THEN GIVEN AND THE FILE WILL BE CREATED ACCORDING TO THE NEW NAMES. THIS MIGHT MAKE IT POSSIBLE TO COPY FROM FOREIGN ANSI-LABELLED TAPES WITH THE BACKUP-SYSTEM.
  - MANUAL CHECK WILL NOW ACCEPT LOWER-CASE CHARACTERS.
- MINOR CHANGE IN LIST-VOLUME TO ALLOW 4 DIGIT FILE-NUMBERS.
- CORRECTED ERRORS IN USER- AND MASTER-LOG MODES CONSERNING OPENING OF LOG-FILES.

NORSK DATA A/S

## NORD SOFTWARE LIBRARY PROGRAM DESCRIPTION

PAGE 1 OF 1

Į

1

PRODUCT	NAME ! ND-NUMBER!CATEGORY BACKUP-SYSTEM ! 10337B ! P !!		
	! ND-NUMBER FOR SOURCE         ! 10347B         !		
ISSUED	DATE 81.11.16 ! BY (INITIALS) LA		
COMPUTERS	1     X     10     !     .     500!     .     .     .       1     1     1     1     1     1     .     .     .		
INSTR.SET	48 BIT FL.!     32 BIT FL.!     COMMERCIAL!       !     !     !		
OP.SYSTEM	X SIN III VS!     . SIN III RT!     . ALONE     !		
DOCUMEN- TATION	NUMBER: 60.151.01		
! 	! TITLE: SINTRAN III UTILITIES MANUAL (Not released yet) !		
PURPOSE ! !	! SUB-SYSTEM FOR FILE COPYING AND BACKUP UNDER ! SINTRAN-III. !		
PROGRAMS (FILES)	PROG.NUMB. NAME TYPE CONTAINING 1 203160B BACKUP-SYSTEM BPUN BACKUP-SYSTEM PROGRAM 1		

## LOADING/OPERATING PROCEDURE, USE

COPY THE FILE BACKUP-SYSTEM: BPUN FROM THE FLOPPY CALLED ND-10337B (BACKUP-SYSTEM FOR SINTRAN-III) TO THE USER WHERE YOU KEEP THE :BPUN FILES (SYSTEM, UTILITY, BPUN-FILES....)

EXAMPLE:

- LOG IN UNDER THE USER WHERE YOU KEEP THE :BPUN FILES: @ENTER-DIRECTORY ND-10337B,FLOPPY-DISK-1<,0> @COPY-FILE "BACKUP-SYSTEM-B:BPUN" (ND-10337B:F-U)BACKUP-SYSTEM:BPUN
- LOG IN UNDER USER SYSTEM @DUMP-REENTRANT BACKUP-SYSTEM-B 0 0 (???)BACKUP-SYSTEM

ONLINE DOCUMENTATION CAN BE OBTAINED FROM THE BACKUP-SYSTEM BY THE FUNCTIONS HELP AND (?)

- HELP : FUNCTION FOR LISTING COMMANDS OR A SUBSET OF COMMANDS. HELP HAS COMMAND-NAME AS PARAMETER. IF HELP IS TYPED AS PARAMETER TO HELP, THE COMMANDS WILL BE LISTED WITH CORRESPONDING EXPLANATIONS.
- (?) : A (?) FOLLOWING AN AMBIGUOUS COMMAND ACTS AS HELP WITH THE COMMAND-NAME AS PARAMETER. IF THE COMMAND IS UNIQUE, AN EXPLANATION OF THIS COMMAND IS GIVEN. A (?) GIVEN IN PLACE OF A PARAMETER WILL EXPLAIN THIS PARAMETER.

THE BACKUP-SYSTEM WILL ACCEPT SEVERAL COMMANDS WRITTEN ON THE SAME LINE. WHEN THESE COMMANDS ARE PROCESSED, THE BACKUP SYSTEM WILL TRACE THEM BY OUTPUTTING THE LEAD-TEXT, COMMAND-NAMES AND PARAMETERS COLLECTED.